


## User Management – Adding users

Use the remote admin tool to connect to the site then click 'User Management' on the left-hand pane to show the screen below.

Type a new name into the user selection drop down then click <Add>. Enter the username and password, confirming the password just below. The backgrounds will be red until the passwords match when they will turn green.

Use the permissions section to enable the user to perform certain actions. A typical set up for a user to view and move the cameras is shown below.

Click the <Apply> button to send the details to the unit. Test the credentials using the SitePoint viewing application.



The screenshot displays the 'Remote Administration Tool' interface. The title bar shows 'Remote Administration Tool' with standard window controls. The menu bar includes 'File', 'Edit', 'View', 'Site', 'Logs', 'Configuration', and 'Help'. The 'teleprecision' logo is on the left, and 'Site Administration' is centered in a yellow banner with an 'Apply' button on the right. A left-hand navigation pane lists various modules: Remote Controller, Sentinel (with a red X), Telemetry Protocols (red X), Camera Configuration (red X), Alarm Channels (red X), Alarm Zones (red X), ARCs (red X), 3G Management (red X), IP Manager (red X), and User Management (with a green checkmark). The main content area is titled 'User Management' and contains a 'User Selection' section with a dropdown menu showing 'user0001' and buttons for 'Add', 'Copy', 'Next', 'Revert', 'Delete', 'Rename', 'Previous', and 'Clear'. Below this are three input fields: 'User Name: fbloggs', 'Password: \*\*\*\*', and 'Confirm Password: \*\*\*\*'. The 'Password' and 'Confirm Password' fields have a green background. A 'Permissions' section features a list of roles: 'All', 'None', 'Admin', 'Installer', and 'Viewer'. To the right of these roles is a list of permissions with checkboxes: 'User Enabled' (checked), 'Password change' (unchecked), 'View cameras' (checked), and 'Steer PTZs' (checked).